WHITE PAPER

Instant openMosix

How to build a working openMosix cluster without touching a compiler

CONTROL PAGE

Document Approvals

Approved for Publication:

Author Name:	Ian Latter
	5 April 2006

Document Control

Document Name:	Instant openMosix; How to build a working openMosix cluster without touching a compiler
Document ID:	instant openmosix.doc-Release-1.0(504)
Distribution:	Unrestricted Distribution
Status:	Release
Disk File:	C:\papers\Instant openMosix.doc
Copyright:	Copyright 2006, Midnight Code

Version	Date	Release Information	Author/s
1.0	05-Apr-06	Release / Unrestricted Distribution	Ian Latter

Distribution

Version	Release to
1.0	Public Release

Table of Contents

1	OVE	RVIEW
2	IT IS	S A LITTLE DAUNTING5
	2.1 2.2 2.3	How do I build an openMosix cluster?
3	ACQ	UIRE THE NEEDED SOFTWARE7
	3.1 3.2 3.3 3.4	DOWNLOAD THE FEDORA CORE 1 OPERATING SYSTEM
4	INST	TALL AND CONFIGURE A NODE
	4.1 4.2 4.3 4.4 4.5 4.6 4.7 4.8	BOOT TO THE FIRST YARROW CD 23 CONFIGURE THE HARDWARE ENVIRONMENT 26 CONFIGURE THE INSTALLATION TYPE AND DISK CONFIGURATION 32 CONFIGURE THE NETWORK ENVIRONMENT 45 CONFIGURE THE TIME, SYSTEM PASSWORD, AND INSTALLATION PACKAGES 50 CUSTOMISE THE NEW SYSTEM 57 INSTALL OPENMOSIX 60 RE-USE THESE STEPS 65
5	BUII	LDING THE CLUSTER
	5.1 5.2 5.3	CLUSTER CONSTRUCTION NOTES
6	CON	CLUSION
7	REF	ERENCES
	7.1 7.2	DISTRIBUTIONS
8	CON	TACT
	8.1 8.2	Additions, Modifications and Deletions

1 Overview

The openMosix community has provided numerous ways for new users to easily and rapidly build clusters. Unfortunately, for the community, there are those new users who want to test openMosix on their own terms but haven't the understanding required to do so. These users are often disheartened by their initial experience and turned away from openMosix, simply because of their own configuration faults.

For these users, this paper will provide a basic, step-by-step process for installing a working openMosix cluster, using only an off-the-shelf Linux distribution and two openMosix RPMs.

This build process will not require code modification or compiling, it will be repeatable, and will not require prior openMosix experience.

It is hoped that this document will help most new openMosix users to understand the openMosix node and cluster configuration in a "clean" environment, allowing them to help themselves – to adapt a working model to their own environments.

2 It is a little daunting

2.1 How do I build an openMosix cluster?

That is the question.

Despite the amount of public information available, it seems that there is no shortage of people who want to try-out openMosix, but are unable to fit the pieces together. While these people seem genuine in their desire to run openMosix, I have struggled to explain concepts, both on and off the public lists, to those with configuration issues, network issues, or a combination of both. In some ways I'm not surprised that these people are here. There is no single resource that offers a clear and systematic approach to building an openMosix cluster. However, I feel frustrated knowing that my efforts are not helping and I can't imagine how frustrating it must feel to be in this configuration limbo, where no-one seems able to help.

To contribute further to this problem, the current Linux kernel series is mature and well set within the 2.6 range. OpenMosix, on the other hand, has only beta versions of its software for the 2.6 kernels. New users rightly expect to use 2.6 kernel versions of the openMosix code for their current kernels. Those with enough knowledge to find and acquire the new code are often not equipped to deal with the issues and errors that come from running the beta kernel software.

It is against this backdrop of confusion and despair that I offer the following documentation. Designed to show anyone how to build an openMosix cluster from a tried-and-true Linux distribution, and with the current production openMosix packages, this installation procedure requires no software compilation.

2.2 What am I about to build?

This guide will take you through the installation of one PC, to the point that it is able to join your cluster as an openMosix node. The cluster constructed from this document can be as simple as two nodes joined via cross-over network cable, or as complicated as a LAN full of nodes with a router for greater network access. In either case, the LAN (or LAN segment) is regarded as being equivalent to a VLAN or a PVLAN – the intention being that all nodes in the cluster are situated within the same LAN segment (broadcast/multicast domain). For the purposes of this document, this architecture will be referred to as a "flat cluster network".

While more complicated architectures are possible, they are not supported by this document. An example of a more complicated architecture might be where groups of nodes, belonging to a single cluster, are found on differing LAN segments (LANs, VLANs or PVLANs), separated by one or many routers.

If you are having difficulty constructing a complicated architecture, then you should validate your basic cluster configuration against this document in a flat cluster network, before continuing.

Unrestricted Distribution

The following diagram shows the flat cluster network architecture – note the minimum requirements;



The IP addressing is arbitrary, but 192.168.100.0/255.255.255.0 will be used, with a default gateway of 192.168.100.1. PC's will be 192.168.100.11-192.168.100.254.

2.3 Hardware pre-requisites and preparation

Before you begin to install any software, check off the following list;

- 1. Working PC (X86 based), with at least 128Mbytes of RAM, 2Gbytes of disk capacity and a bootable CDROM drive (PC x 2)
- 2. CAT-5 cross-over cable (Cable x 1)
- 3. Blank CD-R (CD-R x 2)
- 4. Internet-connected PC with a CD burner.

You will also need a mechanism to put files on the new node. If you are using a cross-over cable network, then you will probably want to use the second CD-R to burn the files on, and transfer them. In the build process these were scp'd from another workstation on the same LAN.

Unrestricted Distribution

3 Acquire the needed software

3.1 Download the Fedora Core 1 Operating System

There is no link from the Fedora Core home page to the Fedora Core 1 (Yarrow) download page. Fedora Core 1 is required as it is the latest Fedora Core OS to have a 2.4 kernel.

Visit the Fedora Core 1 (Yarrow) download page. In your web browser, perform the following.

Action Browse to http://download.fedora.redhat.com/pub/fedora/linux/core/1/	
---	--

This will display the Fedora Core 1 download site.



Select the i386 version.

Action Click "i386"

This will display the Fedora Core 1 (Yarrow) Intel-386 architecture version download options.



Select the ISO version.

Action Click "iso"

This will display the Fedora Core 1 (Yarrow) Intel-386 CDROM images that are available for download.



Select the yarrow-i386-disc1.iso, to download the first Fedora Core 1 CD.

Action Click "yarrow-i386-disc1.iso"

Your browser download manger should then take control of the download;

File	yarrow-i386-disc1.iso	
ierver	download.fedora.redhat.com	
Туре	application/octet-stream	
Size	629.8 MB (660,340,736 byt	
Opens with	🗀 yarrow-i386-disc1.iso	Change
Would you lik	e to Open or Save the file?	
Remembe	er choice and do not show dialog again	

Action Click "Save" to save the download to disk

The download manager should then retrieve the file from the Internet and store it locally.

This may take some time, depending on your Internet connection and available bandwidth.

Allow this download to complete before moving on to section four (4).

Note that only the first CD is required to successfully complete the installation described in this document.

3.2 Download the openMosix kernel package

Visit the openMosix home page. In your web browser, perform the following.

Action Browse to http://www.openmosix.org/

This will automatically redirect to the openMosix SourceForge page.

Unrestricted Distribution



About half-way down that page, you will see the "Latest Release" table. Select the "Download" link for the openMosix kernel.

Action Click "Download" for openMosix-kernel-2.4.26 (version 2.4.26-1)

This will take you to the openMosix project downloads page, and automatically open the kernel package to show the kernel package options.

	t: Files - Opera						
Edit View Book	kmarks Fee <u>d</u> s <u>T</u> ools <u>t</u>	delp					
• 😤 • 🎅	• 🖢 • 🗐 🖉	http://sourceforge.net/project/showfiles.php?group_id=46729&package_id=137967&re	ease_id=288775			RSS	🔹 🔍 100% 💌 📑
	- 10	OSTG -ThinkGeek -Slashdot -ITMJ -Linux.com -NewsForge -freshmeat -	Newsletters -PriceGrabbe	-Jobs -Broadband			
URCE <mark>F(RG</mark>	E.						
one	et 🔪			Log In	Create Account	9	Search
SF.net	Projects My P	age Help					
oftware Map C	Create Project New R	eleases Top Projects New Projects 🕬 Help Wanted				_	
Finet » Projects »	openMosix » Files						2 🖸
onenMosix	v					🛃 Stats	- Activity: 99.88% RSS
opennioaiz				Later Later		1000000000	Street and an and a street of the street of
Summary Ad	imin Home Page Fo	rums Tracker Bugs Support Requests Patches Peature Requests M	all Tasks Docs 5)	creenshots News	UV5 Files		
Ella Dalacas					- Find Solutions	From These Pr	remier Sponsors -
Flie Kelease	es					(m)	=3-
You have s	elected to download	the 2.4.26-1 release.			AMD	42	rackspace
Below is a li	ist of files contained in t	this release. Before downloading, you may want to read the Release Notes.					~
Dackane	Release (data)	Filename	Size (hidar)	Downloads	Archite	cture	Tyme
🖬 openMosi	ix-kernel-2.4.26		Size (oyles)	Dominouus	HICHIC	.cture	1917-0
And in case of the local division of the loc							
Latest	- 2.4.26-1 [Notes]	(2004-12-09-06:51)					
Latest	2.4.26-1 [Notes]	(2004-12-09-06:51) openMosbix-2.4.28-1.bz2	194189	11103	1386		Source .bz2
Latest	- 2.4.26-1 [Notes]	(2004-12-09-06:51) openMosix-2.4.26-1.bz2 openmosix-kernel-2.4.26-openmosix1.athlon.rpm	194189 3041776	11103 2060	1380 1386		Source .bz2 .rpm
Latest	2.4.26-1 [Notes]	(2004 12:06 06:51) openMosik-2:4:20-1.bz2 openmosik-kernel-2:4:28-openmosik1.athion.rpm openmosik-kernel-2:4:28-openmosik1.1386.rpm	194189 3041776 9491539	11103 2060 5387	i380 i386 i386		Source .bz2 .rpm .rpm
Latest	2.4.26-1 [Notes]	(2004 12 09 06.51) openMosik-2 4 20-1 bz2 openmosik-kernel-2 4 26-openmosix1 athlor.rpm openmosik-kernel-2 4 26-openmosix1 1385 rpm openmosik-kernel-2 4 26-openmosix1 1886 rpm	194189 3041776 9491539 10242858 10242858	11103 2060 5387 4866	1386 1386 1386 1386		Source .bz2 .rpm .rpm .rpm
Latest	2.4.26-1 [Notes]	(2004120 00:61) operMosik-2,4,26-1 bz2 opermosik-kernel-2,4,26-opermosik1.athlon.rpm opermosik-kernel-2,4,26-opermosik1.atblon.rpm opermosik-kernel-2,4,26-opermosik1.atblon.rpm opermosik-kernel-2,426-opermosik1.atblon.rpm opermosik-kernel-2,426-opermosik1.atblon.rpm	194189 3041776 9491539 10242858 31013240 10210910	11103 2060 5387 4866 2554 676	i386 i386 i386 i386 i386		Source.bz2 .rpm .rpm .rpm Source.rpm
Latest	2.4.26-1 (Notes)	(200412:00:00:51) opermosite-kernel-2:4:26-opermosist:1.athion.rpm opermosite-kernel-2:4:26-opermosist:1.athion.rpm opermosite-kernel-2:4:26-opermosist:1.athion.rpm opermosite-kernel-2:4:26-opermosist:1.stropm opermosite-kernel-2:4:26-opermosist:1.stropm opermosite-kernel-2:4:26-opermosist:1.stropm opermosite-kernel-2:4:26-opermosist:1.stropm	194189 3041776 9491539 10242858 31013240 10318819 10552180	11103 2060 5387 4866 2554 676 1876	1386 1386 1386 1386 1386 1386		Source.bz2 .rpm .rpm .rpm Source.rpm .rpm
Latest	2.4.26-1 [Notes]	(2004:120:00:00:1) openMosik:2:4:20:1 bst2 openMosik:Kernel-2:4:26-openmosik1:athlon.tpm openmosik:Kernel-2:4:26-openmosik1:athlon.tpm openmosik:Kernel-2:4:26-openmosik1:athlon.tpm openmosik:Kernel-3:4:26-openmosik1:athlon.tpm openmosik:Kernel-3:mp-2:4:26-openmosik1:athlon.tpm openmosik:Kernel-3:mp-2:4:26-openmosik1:athlon.tpm openmosik:Kernel-3:mp-2:4:26-openmosik1:athlon.tpm	194189 3041776 9491539 10242858 31013240 10318819 10552180 39373040	11103 2060 5387 4866 2554 676 1876 2519	1386 1386 1386 1386 1386 1386 1386 1386		Source .bz2 .rpm .rpm Source .rpm .rpm .rpm Source .rpm
Latest Totals:	2.4.26-1 [Notes]	(2004-12:00 00:01) opermositik-kernel-2:4:26-opermositi1.athlon.rpm opermositik-kernel-2:4:26-opermositi1.atblon.rpm opermositik-kernel-2:4:26-opermositi1.1886 rpm opermositik-kernel-2:4:26-opermositi1.athlon.rpm opermositik-kernel-smp:-2:4:26-opermositi1.athlon.rpm opermositik-kernel-smp:-2:4:26-opermositi1.1886 rpm opermositik-kernel-source-2:4:28-opermositi1.1886 rpm opermositik-kernel-source-2:4:28-opermositi1.886 rpm	194189 3041776 9491539 10242858 31013240 10318819 10552180 39373040 114227641	11103 2060 5387 4866 2554 676 1876 2519 31041	1380 1386 1386 1386 1386 1386 1386 1386		Source .bz2 .rpm .rpm Source .rpm .rpm .rpm Source .rpm
Latest Totals:	- 2.4.26-1 (Piotes)	(2004-120 00.63) opermosite-2.4.20-1.bz2 opermosite-kernel-2.4.26-opermosist 1.athion.rpm opermosite-kernel-2.4.26-opermosist 1.386 rpm opermosite-kernel-2.4.26-opermosist 1.athion.rpm opermosite-kernel-3.4.26-opermosist 1.athion.rpm opermosite-kernel-smp-2.4.26-opermosist 1.386 rpm opermosite-kernel-source-2.4.26-opermosist 1.386 rpm 8	194189 3041776 9491539 10242658 31013240 10318819 10552180 39373040 114227641	11103 2060 5387 4866 2554 676 1876 2619 31041	1380 1386 1386 1386 1386 1386 1386 1386		Source .bz2 .rpm .rpm Source .rpm .rpm .rpm Source .rpm
Totals: Find a Tech	2.4.26-1 (pietes)	(200412:00 00:51) openMosik-2:4:26-1 bz2 openmosik-kernel-2:4:26-openmosik1:athion.rpm openmosik-kernel-2:4:26-openmosik1:380 rpm openmosik-kernel-2:4:26-openmosik1:380 rpm openmosik-kernel-2:4:26-openmosik1:athion.rpm openmosik-kernel-3:20:26-openmosik1:athion.rpm openmosik-kernel-3:20:26-openmosik1:386 rpm 8 Sponsor Links	194189 3041776 9491539 10242658 31013240 10318819 10552180 39373040 114227641	11103 2060 5387 4866 2554 676 1876 2519 31041 TG Services	1380 1386 1386 1386 1386 1386 1386 1386 1386		Source .bz2 .rpm .rpm Source .rpm .rpm .rpm Source .rpm
Totals: Find a Tech	☐ 2.4.26-1 (pietes) 1 1 Job	(2004 12:00 00:51) opermosik-kernel-2.4.26-opermosik1.athion.rpm opermosik-kernel-2.4.26-opermosik1.atkion.rpm opermosik-kernel-2.4.26-opermosik1.atkion.rpm opermosik-kernel-2.4.26-opermosik1.athion.rpm opermosik-kernel-5.4.26-opermosik1.athion.rpm opermosik-kernel-5.4.26-opermosik1.athion.rpm opermosik-kernel-5.90.24-00-opermosik1.athion.rpm o	194189 3041776 9491539 10242858 31013240 10318819 10552180 39373040 114227611 OS	11103 2060 5387 4866 2554 676 1876 1876 2519 31041 TG Services	i380 i386 i386 i386 i386 i386 i386 i386 i386		Source.bz2 .rpm .rpm .rpm Source.rpm .rpm Source.rpm
Totals: Find a Tech	☐ 2.4.26-1 (pietes) 1 1 Job	(2004-120 00.63) opermosite.420-1.bz2 opermosite.kernel-2.4.26-opermosist.1.athion.rpm opermosite.kernel-2.4.26-opermosist.1.386 rpm opermosite.kernel-2.4.26-opermosist.1.386 rpm opermosite.kernel-3.4.26-opermosist.1.athion.rpm opermosite.kernel-source-2.4.26-opermosist.1.386 rpm 8 Sponsor Links GUI based IPS. Download Strata Guard Free. IBM Middleware on Linux. Secure. Flexible. And a lower 1	194189 3041776 9491539 10242658 31013240 10318819 10552180 39373040 114227641 005 005 005 005 005 005 005 005 005 00	11103 2060 5387 4866 2554 676 1876 2519 31041 TG Services IS ceGrabber	1380 1386 1386 1386 1386 1386 1386 1386		Bource .bz2 .rpm .rpm .fpm Source .rpm .rpm Source .rpm
Totals: Find a Tech	2.4.26-1 (Pietes)	(2004-120-00.65) opermosite.420-1.bz2 opermosite.kernel-2.4.26-opermosist1.athion.rpm opermosite.kernel-2.4.26-opermosist1.atbion.rpm opermosite.kernel-2.4.26-opermosist1.atbion.rpm opermosite.kernel-2.4.26-opermosist1.athion.rpm opermosite.kernel-source-2.4.26-opermosist1.atbion.rpm opermosite.kernel-	194189 3041776 9491539 10424268 31013240 1031849 10552180 39373040 114227641 CO. Pri Pa	11103 2060 6387 4866 2554 676 1876 2519 31041 TG Services 18 ccGrabber ther Product Offer	i380 i386 i386 i386 i386 i386 i386		Bource Jo2 .rpm .rpm .fm Source .rpm .rpm Source .rpm
Totals: Find a Tech	☐ 2.4.26-1 (Piotes) 1	(2004120 00:61) openMosik-2,4,26-1 bz2 openmosik-kernel-2,4,26-openmosik1.athlon.rpm openmosik-kernel-2,4,26-openmosik1.athlon.rpm openmosik-kernel-2,4,26-openmosik1.athlon.rpm openmosik-kernel-smp-2,4,26-openmosik1.athlon.rpm openmosik-kernel-sm	194189 3041776 9491539 10242658 31013240 10318819 10552180 39373040 114227641 CO. Pri CO. Pri Ge Ge	11103 2060 5387 4866 2554 676 1876 2519 31041 TG Services rs ceGrabber threr Product Offer t Broadband	1380 1386 1386 1386 1386 1386 1386 1386		Bource Jo2 .rpm .rpm Source .rpm .rpm .rpm Source .rpm
Totals:	2.4.26-1 (Piotes)	(2004-1200 00:61) opermositi-2 4 20-1 biz2 opermositi-kernel-2 4 20-opermositi 1.alfnion.rpm opermositi-kernel-2 4 20-opermositi 1.886 rpm opermositi-kernel-3 42-opermositi 1.886 rpm opermositi-kernel-smp-2 4 20-opermositi 1.886 rpm opermositi-kernel-source-2 4 20-opermositi 1.886 rpm 8 Sponsor Links GUI based IPS. Download Strata Guard Free. IBM Middleware on Linux. Secure. Flexible. And a lower 1 ServerBeach - Built by Geeks for Geeks Abod Saccofforgent Abod CGD Privacy Statement Terms. Data Saccofforgent Abod CGD Privacy Statement Terms.	194189 3041776 9491539 1042828 31013240 10318819 10552180 39373040 1142272411 CO. Pri CO. Pri Ge Ge Hitzerzerzet VS Cohn	11103 2060 5387 4866 2554 676 1876 1876 2519 31041 TG Services rs ceGrabber ther Product Offer t Broadband	1380 1386 1386 1386 1386 1386 1386 1386		Bource .bz2 .rpm .rpm Source .rpm .rpm .rpm Source .rpm
Totals: Find a Tech	☐ 2.4.26-1 (pietes) 1 1 Job	(2004120 00:61) openMosic 2,4 26-1 bz2 openmosik-kernel-2,4 26-openmosist 1,3160.rpm openmosik-kernel-2,4 26-openmosist 1,386.rpm openmosik-kernel-2,4 26-openmosist 1,386.rpm openmosik-kernel-3,2 2,26-openmosist 1,386.rpm openmosik-kernel-smp-2,4 26-openmosist 1,386.rpm openmosik-kernel-source-2,4 26-openmosik-kernel-source-2,4 26-openmosik-kernel-source-2,4 26-openmosik-kernel-sou	194189 3041776 9491539 10242859 31013240 10318819 10552180 39373040 114227641 CO. Pri CO. Pri CO. Pri Ge www.ormert from VA SOM	11103 2060 5387 4866 2554 676 1876 2519 31041 TG Services rs ccGrabber ther Product Offer t Broadband	1380 (386 (386 (386 (386 (386 (386 (386) (_	Bource .bz2 .rpm .rpm Source .rpm .rpm Source .rpm Source .rpm

The kernel package that you require is openmosix-kernel-2.4.26openmosix1.i386.rpm.

Action Click "openmosix-kernel-2.4.26-openmosix1.i386.rpm"

You should then be presented with a list of available download locations.

Yew Bookmarks Feeds Tools Help				
🜪 = 🌪 = 🍌 = 🍪 🥖 📄 http://p	rdownloads.sourceforge.net/openmosix/openmosix-kernel-2.4.26-openm	iosix1.i386.rpm?download		- 🔍 100% - 🕤
onet Create, Participate,	Evaluate			
et Projects My Page F	leip			
You are re-	questing file: /openmosix/openmosix-kernel-2. Please select a mirror	4.26-openmosix1.i386.rpm		
Host	Location	Continent	Download	
UFPR C'SL	Curitiba, Brazil	South America	Download	invent
OVH .com	Paris, France	Europe	Download	Simplifying
	Tainan, Taiwan	Asia	Download	the Integratio
OPTUSnet BROADBARD & DIAL UP	Sydney, Australia	Australia	Download	of
UKMIRROR	Kent, UK	Europe	Download	Open Sourc
SURF/net	Amsterdam, The Netherlands	Europe	Download	and Linux
<u>/// 🐨</u>	Minneapolis, MN	North America	Download	
JAIST 北陸 先端科学技術大学院大学	Ishikawa, Japan	Asia	Download	HP LRA brings
mesh solutions and	Duesseldorf, Germany	Europe	Download	Find out more
SWITCH	Lausanne, Switzerland	Europe	Download	
HEAnet	Dublin, Ireland	Europe	Download	
INTERNAP'	Atlanta, GA	North America	Download	-
easynews usener made easy*	Phoenix, AZ	North America	Download	A DESCRIPTION OF
Superb	Seattle, Washington	North America	Download	TigerDirect.com
		Select Prefe	erred Mirror	Besi Computer Deals?
		ufpi	(BR) (FR)	
		ncho	: (TVV) iet (AU)	
		() ken	(UK)	

Select an appropriate location. In the example, the first location was selected.

Action Click "Download" for the closest or fastest location

The download page should be updated to reflect the link that will be used to download the kernel package.

Way Bookmarks Feeds Tools Help	met-2.4.20-openniosix1.1300.1pm - Opera			
🐳 🔹 🔿 - 🔛 - 🌆 🥒 📄 http:	Indownloads sourceforce net (openmosiv/openmosiv-kernel-2.4.26-c	menmosiv1 i386 romžuse, mirror-sufor		• 🖲 100% • 🚽
	OSTG -ThinkGeek -Slashdot -ITMJ -Linux.com -NewsForge	-freshmeat -Newsletters -PriceGrabber -Jobs -Broa	adband	
Perfo	Ads by Lustre Scalable Storage ormance with High Availability Open-source Cluster File System www.clusters.com	Google Continuent uni/cluster Database high availability and scalab evaluation! www.continuent.com	ility. Free	
onet Create, Participat	e, Evaluate			
t Projects My Page our download should begin shor	нер rtly. If it does not, try http://ufpr.dl.sourceforg openmosix1.i386.rpm or choose a di	e.net/sourceforge/openmosix/oper fferent mirror	nmosix-kernel-2.4.26-	Visual Studio 2002
You ar	e using mirror:			Spot the Difference
ufpr.dl.	sourceforge.net	UFPR C	SL.	
Host	Location	Continent	Download	
SWITCH	Lausanne, Switzerland	Europe	Download	
	Atlanta GA	North America	Download	
The Identification Exchange	· manual or ·			
HEAnet	Dublin, Ireland	Europe	Download	Over 400 new features help you
SURF/net	Dublin, Ireland Amsterdam, The Netherlands	Europe	Download Download	Over 400 new features help yo build cleaner cod
HEAnet () SURF.net	Dublin, Ireland Amsterdam, The Netherlands Minneapolis, MN	Europe Europe North America	Download Download Download	Over 400 new features help you build cleaner coo The difference is obvious.
SURF.net	Dublin, Ireland Arnsterdam, The Netherlands Minneapolis, MN Sydney, Australia	Europe Europe North America Australia	Download Download Download Download	Over 400 new features help you build cleaner coo The difference is obvious.
ELEMENT IN THE STATE	Dublin, Ireland Amsterdam, The Netherlands Minneapolis, MN Sydney, Australia Duesseldorf, Germany	Europe Europe North America Australia Europe	Download Download Download Download Download	Over 400 new features help yo build cleaner cod The difference is obvious.
HEAnet	Dublin, Ireland Arnsterdam, The Netherlands Minneapolis, MN Sydney, Australia Duesseldorf, Germany Tainan, Taiwan	Europe Europe North America Australia Europe Asia	Download Download Download Download Download	Over 400 new features help yo build cleaner coo The difference is obvious.
Ret Solutions of Ret Solutions of Ret Solutions of Ret Solutions of Ret Solutions of Ret So	Dublin, Ireland Arnsterdam, The Netherlands Minneapolis, MN Sydney, Australia Duesseldorf, Germany Tainan, Taiwan Kent, UK	Europe Europe North America Australia Europe Aaia Europe	Download Download Download Download Download Download	Over 400 new features help you build cleaner coo The difference is obvious.
	Dublin, Ireland Arnsterdam, The Netherlands Minneapolis, MN Sydney, Australia Duesseldorf, Germany Tainan, Taiwan Kent, UK Ishikawa, Japan	Image: Constraint of the second of the se	Download Download Download Download Download Download Download	Over 400 new features help you build cleaner coo The difference is obvious.

The page should auto-refresh to download the file. Your browser download manger should then take control of the download;

Do	ownload file		X
	File	openmosix-kernelpenmosix1.i386.rpm	
	Server	ufpr.dl.sourceforge.net	
	Туре	application/x-redhat-packag	
	Size	9.1 MB (9,491,539 bytes)	
	Opens with	🛅 openmosix-kernel-2.4.26-o Change	
	Would you like	e to Open or Save the file?	
	Remembe	r choice and do not show dialog again	
	Open	Save Cancel Help	•

Action Click "Save" to save the download to disk

The download manager should then retrieve the file from the Internet and store it locally.

Transfers 02:08				
🐹 Stop 🛛 🗐 Retransfer 🙆 View 🔻 Quick do	wnload			
Name	Size	Progress	Time	Speed
● I openmosix-kernel-2,4,26-openmosix1,i386,rpm	9.1 MB	27.0%	2:08	52.7 KB/s
From				
То				
Size				
Transferred				

Allow this download to complete before moving on to section four (4).

3.3 Download the openMosix tools package

Return to the openMosix home page. In your web browser, perform the following.

Action Browse to http://www.openmosix.org/

This will automatically redirect to the openMosix SourceForge page.

Unrestricted Distribution



About half-way down that page, you will see the "Latest Release" table. Select the "Download" link for the openMosix tools.

Action Click "Download" for openMosix-user (version 0.3.6.2)

This will take you to the openMosix project downloads page, and automatically open the user (tools) package to show the tools package options. .

View Bookmarks Feeds Loof	ls <u>H</u> elp					
• 👻 • 🍺 • 🔣 🥖	//sourcefor	ge.net/project/showfiles.php?group_id=46729&package_	jd=396278release_id=256794		R	s 🔹 🔍 100% 💌 📑
	OST	G -ThinkGeek -Slashdot -ITMJ -Linux.com -NewsForge	-freshmeat -Newsletters -PriceGrabber	-Jobs -Broadband		
	Performance	Lustre Scalable Storage with High Availability Open-source Cluster File System www.cluster6.com	Continuent uni/ Database high availability a evaluatior www.continuen	cluster nd scalability. Free I t.com		
aceFC RGE				Log In - Cre	eate Account 🤍	Search
.net Projects N	lly Page Help					
vare Map Create Project Ne	w Releases Top Pro	ojects New Projects 🚥 Help Wanted		_	_	
et » Projects » openMosix » Files						<u> </u>
enMosix					M 31	ats - Activity: 99.88%
File Releases You have selected to downlo	oad the 0.3.6-2 relea	ise.	nen Neten	A	Find Solutions From Thes	e Premier Sponsors -
The Releases You have selected to downlo Below is a list of files contained	oad the 0.3.6-2 relea d in this release. Befo	ise. re downloading, you may want to read the Relea	ise Notes.	A	Find Solutions From Thes	e Premier Sponsos-
File Releases You have selected to downlu Below is a list of files contained ckage Release (date)	o <mark>ad the 0.3.6-2 relea</mark> d in this release. Befo) Filename	tse. re downloading, you may want to read the Relea	ise Notes. Size (bytes)	Downloads	Find Solutions From Thes	e Premier Sponsors recksperse
File Releases You have selected to downly Below is a list of files contained ckage Release (date) openmosix-user	o <mark>ad the 0.3.6-2 relea</mark> d in this release. Befo) Filename	ise. re downloading, you may want to read the Relea	ise Notës. Size (bytes)	A	Find Solutions From Thes	e Premier Sponsors -
File Releases You have selected to downly Below is a list of files contained chage Release (Jane) openmosiz-user at 0.3.6-2 piet	and the 0.3.6.2 relea d in this release. Befor Filename e=] (2004-07-29 00:00)	tse. re downloading, you may want to read the Relea new 12 (1997) - 1996 mm	ise Notes. Size (kytes) 120291	Downloads	Architecture	Premier Sponos-
File Releases You have selected to downle Below is a list of files contained ckage Release (date) openmosix-user et 0.3.6-2 pick	ad the 0.3.6.2 relea d in this release. Befor Filename es] (2004-07-20 00:00) openmosis-to openmosis-to	ise. re downloading, you may want to read the Relea pls=0.3 6=21886 mm pls=0.3 6=21886 mm	ise Notes. Size (۱۰/۹۵) 170291 519132	Downloads	Architecture	Type
File Releases You have selected to downl. Below is a list of files contained ckage Release (date) openmosix-user at 0.0.3.6-2 plea	bad the 0.3.6-2 releaded d in this release. Before b) Filename est] (2004-07-29 00.00) openmosib-tor openmosib-tor openmosib-tor	ise. re downloading, you may want to read the Relea ols-0.3.6-2.1386 mm ols-0.3.6-2.1386 mm ols-0.3.6-2.src rpm ols-0.3.6-2.tar.gz	sse Notes. Size (bytes) 170291 519132 515181	Downloads	Architecture	Type rpm Source .rpm .gz
File Releases You have selected to downli- Below is a list of files contained ckage Release (date: openmosix-user ant 0.3.6-2 peet	and the 0.3.6-2 release in this release. Before Filename est (2004-07-29 00 00) openmosit-to openmosit-to copenmosit-to README-open	nse. re downloading, you may want to read the Relet of the second second second second second second second second of the second second second second second second second second second second	Size (bytes) Size (bytes) 170291 519132 515181 8352	9763 1704 17327 2412	Architecture	Fremiel Sponor-
Tile Releases You have selected to downl. Below is a list of files contained ckage Release (dats openmosix-user ent 0.3.6-2 peat als: 1	and the 0.3.6-2 release in this release. Before Filename est (2004-07-20 00.00) openmosis/eo openmosis/eo openmosis/eo README-oper 4	tse. re downloading, you may want to read the Relea ols-0.3.6-2,1986 rom ols-0.3.6-2,2src rpm ols-0.3.6-2 tar gr mmosit-tools bt	Size (bytes) Size (bytes) 170291 619132 619132 619138 8352 1212956	Downloads 9763 1704 7327 2412 21206	Architecture	Type pm Source .rpm .gz text
File Releases You have selected to downli Below is a list of files contained ckage Release (data openmosix-user ent 0.0.3.6-2 piec als: 1 Find a Tech Job	and the 0.3.5.2 relation aid in this release. Before b) Filename acj (2004.07.29 00.00) openmosile-log openmosile-log README-opel 4	Isse. re downloading, you may want to read the Relea of the Control of the Release of the Control of the Release of the Control of the Release of the Releas	sse Notes. Size (bytes) 170281 519132 515181 8352 1212956 OST	Downloads 9763 1704 7327 2412 21206 G Services	Architecture Architecture 1386 1386 1386 Platorm- Independent	Type rpm Source rpm .gz text
Tile Releases You have selected to downli Below is a list of files containen ckage Release (date openmosix-user ent 0.0.3.6-2 plet lafs: 1 Find a Tech Job	oad the 0.3.6-2 release in this release. Before o Filename est (2004.07-20.0000) openmosit-to openmosit-to openmosit-to README-open 4	Iss. re downloading, you may want to read the Relea Pls=0.3.8-2.1336 mm Dis=0.3.8-2.9 mm Dis=0.3.8-2.12 gr mmostic-loois bit Sponsor Links GoToMyPC - Access Your PC from Anywf	sse Notes. Size (bytes) 170291 519132 515181 8352 1212956 051 ere Job	Downloads 9763 1704 7327 2412 21206 'G Services	Architecture Architecture 1386 1386 1386 Platorm- Independent	Type rpm Source rpm .gz text
File Releases You have selected to downli- Below is a list of files containen ckage Release (data openmosix-user at 0.0.3.6-2 pter at 0.0.3.6-2 pter ats: 1 Find a Tech Job	and the 0.3.6.2 relies in this release. Before the second second second opermosite of relation opermosite of README-oper 4	Iss. re downloading, you may want to read the Relea als=0.3.8-2.1286 mm als=0.3.8-2.36c pm als=0.3.8-2.36c pm als=0.3.8-2.45 mm be 0.3.8-2.45 mm be 0.3.8-2.55 mm be	Size (bytes) 5ize (bytes) 170281 5i9132 5i5181 8352 1212956 ere Job Price Price	Downloads 9763 1704 7327 2412 21206 C Services seGrabber	Architecture Architecture 1386 1386 1386 Platorm- Independent	Type rpm Source rpm .gz text
File Releases You have selected to downli Below is a list of files contained ckage Release (data openmosix-user ent 0.0.3.6-2 plet als: 1 Find a Tech Job	and the 0.3.6.2 relies in this release. Before the second second second opermosite to opermosite to README-oper 4	Iss. re downloading, you may want to read the Relea als=0.3.8-2.1286 mm als=0.3.8-2.36c pm als=0.3.8-2.36c pm als=0.3.8-2.47 pm beta 3.8-2.36c pm beta 3.8-2.36c pm beta 3.8-2.1286 mm beta 3.8-2.12	Size (bytes)	Downloads 9763 1704 7327 2412 21206 G Services s G Services s eGrabber mer Product Offers	Architecture Architecture 1386 1386 1386 Platorm- Independent	Type rpm Source rpm .gz text
File Releases You have selected to downl. Below is a list of files container ckage Release (date openmosix-user at 0.3.6-2 pex als: 1 ind a Tech Job	and the 0.3.6-2 relea in this release. Before Flename as: (2004-07-20 00.00) openmosit-bo openmosit-bo openmosit-bo openmosit-bo openmosit-bo openmosit-bo openmosit-bo openmosit-bo	ISSE. re downloading, you may want to read the Relea ols=0.3.6-2,1386 rom ols=0.3.6-2,1386 rom ols=0.3.6-2,arc.rpm ols=0.3.6-2,arc.rpm ols=0.3.6-2,arc.rpm ols=0.3.6-2,arc.rpm ols=0.3.6-2,arc.rpm ols=0.3.6-2,1386 rom ols=0.3.6-2,1386 rom ols=0.5.6-2,1386 rom ols=0.5.6-2,138	Size (bytes)	Downloads 9763 1704 7327 2412 21206 G Services eGrabber ner Product Offers Broadband	Architecture Architecture 1386 1386 1386 Platform- Independent	Type pm Source .pm .gz text

The tools package that you require is openmosix-tools-0.3.6-2.i386.rpm.

Action Click "openmosix-tools-0.3.6-2.i386.rpm"

You should then be presented with a list of available download locations.

rsing Download Server: /open	mosix/openmosix-tools-0.3.6-2.i386.rpm - Opera			_
View Bookmarks Feeds Tools	; Helb			
E · · · · · · · · · · · · · · · · · · ·	http://prdownloads.sourceforge.net/openmosix/openmosix/cols-U.3.6-2 OSTC ThickCeels Sizebute ITML Lioux.com NewsEcret		adhand	· · · · ·
	Ads by	Google		
	Lustre Scalable storage Performance with High Availability Open-source Cluster File System www.clusterfs.com	Database high availability and scalab evaluation www.continuent.com	ility. Free	
ceFCRGE [®] onet Create	e, Participate, Evaluate			
t Projects My P	'age Help			
	You are requesting file: /openmosix/openmos Please select a mirror	six-tools-0.3.6-2.i386.rpm		
Host	Location	Continent	Download	
SURF/net	Amsterdam, The Netherlands	Europe	<u>Download</u>	invent
	Atlanta, GA	North America	Download	Simplifying
mesh solutions me	Duesseldorf, Germany	Europe	Download	the Integration
Casynews	Phoenix, A7	North America	Download	of
HEAnet 🍭	Dublin, Ireland	Europe	Download	Open Source
AIST 北陸 先编科学技術大学微大学	Ishikawa, Japan	Asia	Download	and Linux
SWITCH	Lausanne, Switzerland	Europe	Download	
OPTUSnet BROADBAND & DIAL UP	Sydney, Australia	Australia	Download	it all togethe
	Tainan, Taiwan	Asia	Download	
OVH .com	Paris, France	Europe	Download	Find out more
14.80	Minneapolis, MN	North America	Download	
	Seattle, Washington	North America	Download	
UFPR C'SL	Curitiba, Brazil	South America	Download	Constant of
UKMIRROR Service	Kent, UK	Europe	Download	Sponsored Downloa
		Select Prefe	rred Mirror	Global seminar on Linux migration
page Browsing Download Serv				

Select an appropriate location. In the example, the first location was selected.

Action Click "Download" for the closest or fastest location

The download page should be updated to reflect the link that will be used to download the tools package.

: View Bookmarks Feeds Tools	Help			
🜪 • 🔿 • 🐎 • 🍲 🥖	http://prdownloads.sourceforge.net/openmosix/openmosix-tools-0.3.6-2.	i386.rpm?use_mirror=surfnet		• 🔍 100% •
	OSTG - ThinkGeek - Slashdot - ITMJ - Linux.com - NewsForge	-freshmeat -Newsletters -PriceGrabber -Jobs -Bro	adband	
	Lustre Scalable Storage Performance with High Availability Open-source Cluster File System www.clusterfs.com	Continuent uni/cluster Database high availability and scalat evaluation www.continuent.com	pility, Free	
eceFCRGE [®] onet Create, I	Participate, Evaluate			
et Projects My Pag	ge Help			
our download should beg	in shortly. If it does not, try http://surfnet.dl.sourceft 2.i386.rpm or choose a differer	orge.net/sourceforge/openmosix/o nt mirror	penmosix-tools-0.3.6-	CURIOUSLY STROM MAGNET
	You are using mirror:	c	Enat	NEODYMIUN
s	urfnet.dl.sourceforge.net	301		IRON-BORON RARE EARTH M A G N E T
Host	Location	Continent	Download	
mesh solutions m	Duesseldorf, Germany	Europe	Download	
UNIVERSITY OF KENT	Kent, UK	Europe	Download	
	Atlanta, GA	North America	Download	
	Seattle, Washington	North America	Download	Company de C
	Tainan, Taiwan	Asia	Download	CINE S
UFPR C'SL	Curitiba, Brazil	South America	Download	A A A A
HEAnet ()	Dublin, Ireland	Europe	Download	
SW/ITCH	Lausanne, Switzerland	Europe	Download	
easynews usenet mode easy*	Phoenix, AZ	North America	Download	Get i
SURF/net	Amsterdam, The Netherlands	Europe	Download	Think Geel
<u>/// (m.</u>	Minneapolis, MN	North America	Download	TigerDirect.com Best Computer Deals

The page should auto-refresh to download the file. Your browser download manger should then take control of the download;

openmosix-tools-0.3	.6-2.i386.rpm	
surfnet.dl.sourcefor	ge.net	
application/x-redhat-	packag	
167 KB (170,291 byt	es)	
🗀 openmosix-tools-0.3	.6-2.i3	Change
o Open or Save the file?		
choice and do not show dia	alog again	
Save	Cancel	Help
	openmosix-tools-0.3 surfnet.dl.sourceford application/x-redhat- 167 KB (170,291 byt ic openmosix-tools-0.3 o Open or Save the file? choice and do not show dia	openmosix-tools-0.3.6-2.i386.rpm surfnet.dl.sourceforge.net application/x-redhat-packag 167 KB (170,291 bytes) openmosix-tools-0.3.6-2.i3 o Open or Save the file? choice and do not show dialog again

Action Click "Save" to save the download to disk

The download manager should then retrieve the file from the Internet and store it locally.

Transfers 00:09				
🐹 Stop 🛛 💋 Retransfer 🙆 View 🔻 Quick dow	wnload			
Name	Size	Progress	Time	Speed
openmosix-tools-0.3.6-2.i386.rpm	167 KB	Done		
penmosix-kernel-2.4.26-openmosix1.i386.rpm	9.1 MB	97.2%	0:09	26.6 KB/s
From				
То				
Size				
Transferred				

Allow this download to complete before moving on to section four (4).

3.4 Burn the software to CDROM

Depending on the operating system and CD utilities that you have available to you, there are a number of ways to burn this content to CDROM – these will not be described here.

Ensure that the Yarrow ISO image is burnt to the first disc (as a whole disk image).

Action Burn "yarrow-i386-disc1.iso" as a whole disk image, to a CD-R

Then burn the two openMosix files to the second disc.

Action Burn "openmosix-kernel-2.4.26-openmosix1.i386.rpm" and "openmosix-tools-0.3.6-2.i386.rpm" to the second CD-R

4 Install and configure a node

4.1 Boot to the first Yarrow CD

Insert the Yarrow (Fedora Core 1) CD into the CDROM drive of the computer to be built as the new node. Boot the computer.



The PC will boot to the following screen.



The OS installation will be performed as a "text mode" installation. To install RedHat's Fedora Core 1 in this mode, boot with option "linux text".

Action At the CD boot prompt, enter "linux text" and press enter



Allow the installer to start the installation program. It will begin with the media checking program.



There is no need to check the CD media, select "Skip".

The Yarrow installation program will now begin to take installation configuration options.

4.2 Configure the hardware environment

Welcome to the real start of Yarrow installation process. The installer will display the "Welcome to Fedora Core" screen.



At the "Welcome to Fedora Core" screen, select "Ok".



The installer will move on to language selection.

🗐 FC1 Node1 - VMware Workstation 📃 🗆 🔀
File Edit View VM Team Windows Help Fedora Core (C) 2003 Red Hat, Inc.
Language Selection What language would you like to use during the installation process? Chinese(Simplified) Chinese(Traditional) Croatian # Czech Danish Dutch English French
<tab>/<alt-tab> between elements <space> selects <f12> next screen</f12></space></alt-tab></tab>

As this document has been written in English, this will be used as the language default. At the "Language Selection" screen, select "English", then "Ok".

Action	At the Language Selection screen, select "English", then select
ACTION	"Ok" and press enter

The installer will move on to keyboard selection.

🗐 FC1 Node1 - VMware Wor	kstation	
File Edit View VM Team Fedora Core (C) 2003 R	Windows Help ed Hat, Inc.	
	Keyboard Selection Which model keyboard is attached to this computer? slovene speakup speakup-1t sv-latin1 trq ua ub Ub DK	
<tab>/<alt-tab> betw</alt-tab></tab>	een elements <space> selects <f12> next scre</f12></space>	en

As this document has been written in Australia, local keyboard type (US) will be used as the default. At the "Keyboard Selection" screen, select "us", then "Ok".

Action	At the Keyboard Selection	screen, select	"us", th	en select "Ok"
Action	and press enter			

The installer will move on to mouse selection.



This system will not be configured with an X11 (X-Windows) interface – there will be no Graphical User Interface. No mouse will be required.

At the "Mouse Selection" screen, select "No - mouse", then "Ok".

Action	At the Mouse Selection screen, select "No - mouse", then select
ACTION	"Ok" and press enter

The installer will move on to monitor selection.



As this system will not be configured with an X11 interface, there won't be a requirement for any graphical display modes. The monitor won't leave its default 80x25 terminal mode.

At the "Monitor Configuration" screen, select "Ok" (even for "Unprobed Monitor" types).



The installer will move on to the monitor validation screen.



If the monitor on the PC being built is not recognised, you may be prompted to accept the default configuration settings. These settings should be fine for any monitor not switching to high resolution graphical modes.

If it appears, at the "Monitor Unspecified" screen, select "Proceed".



With the hardware environment configured, the Yarrow installation program will now begin to tune the type of installation, and partition the disks accordingly.

4.3 Configure the installation type and disk configuration

Now that he hardware environment has been configured, the installation process will identify the build type, and then partition the local disks. The "Installation Type" screen will be displayed.



As a demonstration, there is no need for a complex or massive installation in order to support openMosix. The build type selected here will be used to minimise the total quantity of software installed.

At the "Installation Type" screen, select "Custom" and then "Ok".

Action	At the Installation Type screen, select "Custom", then select
Action	"Ok" and press enter

The installer will move on to the disk partitioning setup screen.

Unrestricted Distribution



During testing it was found that the "Autopartition" option would not always work. For reliability, the "Disk Druid" (manual) option has been documented.

At the "Disk Partitioning Setup" screen, select "Disk Druid".

Action	At the Disk Partitioning Setup screen, select "Disk Druid", and
Action	press enter

The installer will move on to the disk partitioning warning screen.



All data on your computer's hard disk will be destroyed. Accepting this warning message will lead to the unrecoverable deletion of all of your data!

At the disk partitioning "Warning" screen, select "Yes".

Action	At the disk partitioning Warning screen, select "Yes", and
	press enter

The installer will move on to the disk partitioning configuration screen.

NB: If you are not using a blank hard disk (i.e. this hard disk has had a previous Operating System installed) then you will need to delete any existing partitions.

🗐 FC1 Node1 - VMware Workstat	ion		_ 🗆 🛛
File Edit View VM Team Wind	ows Help		
reaura cure (C) 2005 nea n	at, IIIC.		
	Pantitioning		
Device St	art End Size	Type Mount Point	-
Free space	1 768 1535M	Free space	#
New	Delete	D OK Back	
F1-Help F2-New	F3-Edit F4-Delete	F5-Reset F12-OK	

Starting with a blank disk (see note above if old partitions exist) At the disk "Partitioning" screen, select "New".

Action At the disk Partitioning screen, select "New", and press enter

The installer will move on to the add partition screen.



The first file system is swap – this is the computer's swap-space for use in cases of high memory demand.

Select the file system type of "swap", enter the size in Mbytes of "256", then select "Ok".

Action	At the Add Partition screen, select the File System Type of
	"swap", enter the Size of "256", select "Ok" and press enter

The installer will move on to the disk partitioning configuration screen.
FC1 Node1 - V	Mware Work	station					
e Edit View	VM Team	Windows H	Help				
lora Core (C) 2003 Re	d Hat, I	nc.				
			- Par	titioning	ŀ		
Devi	ce	Start	End	Size	Туре	Mount Point	
/dev/sda					34		
sda1		1	128	255M	swap		#
Free sp	ace	129	768	1280M	Free space		
Nout	E A S		Delete	PA		Pack	24
New	La I	5 B	perece	I III		Dack	
E1-Helm	F2-Neu	F3-	Fdit	F4-Delet	e F5-Rese	+ F12-0K	

You should now have one partition, of type "swap", in the partition table. The rest of the disk should be labelled as "Free space". Now, create the system partition.

At the disk "Partitioning" screen, select "New".

Action At the disk Partitioning screen, select "New", and press enter

The installer will move on to the add partition screen.



The second file system is the system partition – this is going to be the partition used for the computer's root file system, and will house all of the software stored on this computer. It will fill all of the remaining space of the disk – this must be at least 1.2Gbytes.

Enter a Mount Point of "/", select the file system type of "ext3", select the "Fill all available space" option, then select "Ok".

	At the Add Partition screen, enter a Mount Point of "/", select
Action	the File System Type of "ext3", select the "Fill all available space" option select "Ok" and press enter
	space option, beteet on and press cheer

The installer will move on to the disk partitioning configuration screen.

e Edit View VI lora Core (C)	M Team Windows 2003 Red Hat,	Help , Inc.				
		Par	titioning			
Devic	e Start	t End	Size	Туре	Mount Point	-
∕dev∕sda sda1 sda2	: 64:	L 640 L 768	1279M 256M	ext3 swap	/	#
New	Edit	Delete	RA	ID OX	Back	

You should now have two partitions; sda1 of at least 1.2Gbytes at mount point "/", and sda2 of about 256Mbytes of type "swap", in the partition table. There shouldn't be and free space left on the disk.

At the disk "Partitioning" screen, select "Ok".

Action At the disk Partitioning screen, select "Ok", and press enter
--

The installer will move on to the boot loader configuration screen.



The default boot loader is Grub. It is a suitable boot loader for this computer. At the disk "Boot Loader Configuration" screen, select "Ok".

Action	At the disk Boot Loader Configuration screen, select "Ok", and	
Action	press enter	

The installer will move on to the boot loader configuration options screen.

🔤 FC1 Node1 - VMware Workstation	
File Edit View VM Team Windows Help	
Fedora Core (C) 2003 Red Hat, Inc.	
Boot Loader Configuration	
a sour sour ign action	
A few systems will need to pass special options to the kernel at boot time for the system to function properly. If you need	
to pass boot options to the kernel, enter them now. If you	
don't need any or aren't sure, leave this blank.	
hdc=ide-scsi	
[] Force use of LBA32 (not normally required)	
OK	
<tab>/<alt-tab> between elements <space> selects <f12> next so</f12></space></alt-tab></tab>	creen

The default boot loader options are fine. In the test case (shown) the VMWare CDROM drive was automatically configured with the option "hdc=ide-scsi" – there is no need to add or remove any options to this dialogue.

At the disk "Boot Loader Configuration" options screen, select "Ok".

Action	At the disk Boot Loader Configuration options screen, select
Action	"Ok", and press enter

The installer will move on to the boot loader configuration password screen.



There is no need for a Grub password, do not set this option.

At the disk "Boot Loader Configuration" password screen, select "Ok".

Action	At the disk Boot Loader Configuration password screen, select
ACUON	"Ok", and press enter

The installer will move on to the boot loader configuration OS screen.



As this is not a multi-boot machine (this computer has only the Fedora Core 1 OS installed on it) default partition is fine.

NB: Observe the device used for the Boot Loader Configuration (/dev/sda1 in this case). The disk device (/dev/sda in this case) will be used during the openMosix installation, later in the build process.

At the disk "Boot Loader Configuration" OS screen, select "Ok".

Action	At the disk Boot Loader Configuration OS screen, select "Ok",
ACIION	and press enter

The installer will move on to the boot loader configuration installation screen.



The default disk or partition is fine for the Grub installation.

At the disk "Boot Loader Configuration" installation screen, select "Ok".

Action	At the disk Boot Loader Configuration installation screen,
Action	select "Ok", and press enter

With the installation type and disk configuration established, the Yarrow installation program will now begin to configure the networking environment for this computer.

4.4 Configure the network environment

With the build type selected and local disk partitions configured, the installation process will ask for the network configuration (including the firewall). The "Network Configuration for eth0" screen will be displayed.



For simplicity's sake, this build assumes that you don't have a DHCP server on your network (LAN). This, then, allows you to use two PCs with a cross-over cable as the local LAN segment. The IP addressing selected here is arbitrary, but all PCs must be in the same subnet (i.e. all in 192.168.100.x/255.255.255.0). PC's will be assumed to be in the range of 192.168.100.11-192.168.100.254.

At the "Network Configuration for eth0" screen, de-select "Configure using DHCP", enter the "IP Address", enter the "Netmask" and then select "Ok".

	At the Network Configuration for eth0 screen, de-select
Action	"Configure using DHCP", enter the "IP Address", enter the
	"Netmask", then select "Ok" and press enter

The installer will move on to the miscellaneous network settings screen.

🔄 FC1 Node1 - VMware Workstation	
File Edit View VM Team Windows Help Fedora Core (C) 2003 Red Hat, Inc.	
Miscellaneous Network Settings Gateway: 192.168.100.1 Primary DNS: Secondary DNS: Tertiary DNS: Back	
<tab><<flt-tab> between elements i <space> selects i <f12> ;</f12></space></flt-tab></tab>	next screen

The default gateway for this LAN segment does not need to be an actual device on the LAN (as noted in the cross-over example) but does need to be configured. Also, as you may be using a cross-over cable, and as there is no need for it anyway, no DNS servers will be entered.

At the "Miscellaneous Network Settings" screen, enter the "Gateway" and then select "Ok".

Action	At the Miscellaneous Network Settings screen, enter the	
Action	"Gateway", then select "Ok" and press enter	

The installer will move on to the hostname configuration screen.



With no DHCP server in this network, the hostname will be entered manually. The actual hostname is arbitrary so make it meaningful to your situation.

At the "Hostname Configuration" screen, select "manually", enter the hostname and then select "Ok".



The installer will move on to the firewall screen.



To keep this test as basic as possible, no firewall will be installed. This is a valid configuration for any private cluster network, but is considered High Risk in multi-user environments.

At the "Firewall" screen, select "No firewall" and then select "Ok".



The installer will move on to the firewall warning screen.



Rightly, the installation program is warning you that you have no firewall configured. See above for the configuration reasoning.

At the "Warning – No Firewall" screen, select "Proceed".

Action	At the Warning - No Firewall screen, select "Proceed" and press
Action	enter

With the network and firewall configuration established, the Yarrow installation program will now begin to configure the time, system (root) password and packages to be installed on this computer.

4.5 Configure the time, system password, and installation packages

This is the final stage of the Yarrow build process. This section of the installation will configure additional language support, time, the system (root) password, and any packages that are to be installed on this computer.

The "Language Support" screen will be displayed.



As this document has been written in English, this will be used as the language default. At the "Language Support" screen, select "English (USA)", then "Ok".

Action	At the Language Support screen, select "English (USA)", then
Action	select "Ok" and press enter

The installer will move on to the time zone selection screen.



As this document has been written in Australia, the local time zone has been selected. At the "Time Zone Selection" screen, select "Australia/NSW", then "Ok".

Action	At the	Time	Zone Selection screen,	select	"Australia/NSW",	then
Action	select	"Ok″	and press enter			

The installer will move on to the root password configuration screen.



The system (root) password is arbitrary. Select a password that is agreeable with your local password policy. For this documentation, the password selected was "password" – it is not agreeable with any known password policy.

At the "Root Password" screen, enter the "Password" of "password", enter the "Password (confirm)" of "password" then "Ok".

	At the Root Password screen, enter the "Password" of
Action	"password", enter the "Password (confirm)" of "password", then
	select "Ok" and press enter

The installer will move on to the package group selection screen.



The openMosix cluster node requires no additional software. In this example, every package was disabled. Should you elect to enable additional packages, adjust the disk space requirements accordingly, and be prepared to download and burn additional Yarrow CD's.

At the "Package Group Selection" screen, de-select all options, then select "Ok".



The installer will move on to the installation start screen.



This information-only page is a notification of the installation log.

At the "Installation to begin" screen, select "Ok".

Action	At the Installation To Begin screen, select "Ok" and press
Action	enter

The installer will install the Yarrow Operating System – this should only take a few minutes. Once it has done that it will move on to the boot diskette screen.



There is no need to create a boot diskette – these PCs are far too easy to rebuild from installation media.

At the "Boot Diskette" screen, select "No".

Action At the Boot Diskette screen, select "No" and press enter

The installer has exhausted all configuration options. The final screen will be the completion screen.

White Paper Instant openMosix How to build a working openMosix cluster without touching a compiler



The installation is complete! At the "Complete" screen, press enter.

Action At the Complete screen, press enter
--

The installer has completed, the PC is now rebooting. Next, you will turn this Fedora Core 1 (Yarrow) PC into an openMosix node.

4.6 Customise the new system

The PC will boot to the following boot menu.



This boot menu will display on every boot. The default option is correct. You can either choose to let it time-out (after about 10 seconds) or you can press enter.

At the "Boot Menu" screen, press enter.

Action At the Boot Menu screen, press enter

The PC will proceed to boot the Yarrow OS, where you can then login as root.

Action	At the login: prompt, enter the username "root", press enter,
Action	then the enter the root password "password", and press enter

You are now logged on as the super-user (root) on this system, and at the system prompt.

Unrestricted Distribution



Despite the build type of "Custom" with no additional "packages", the default Yarrow installation runs a number of unnecessary services (daemons). These services can (and should) be disabled.

At the system prompt, enter the "chkconfig" commands required to disable the unneeded services.

Each command disables one service.

FC1 Node1 - VMware Workstation	
File Edit View VM Team Windows Help	
Fedora Core release 1 (Yarrow) Kernel 2.4.22–1.2115.nptl on an i686	
fc1-node1 login: root	
Password:	
Last login: Mon Mar 27 22:54:02 on ttyl	
Irooterci-nodel rootl# chkcomily acple off	
[rooterc1-node1 root]# chkconfig adma off	
[root] hold root] # Chkconfig and off	
[root0fc1-node1 root]# chkconfig iptables off	
[root@fc1-node1 root]# chkconfig isdn off	
[root@fc1-node1 root]# chkconfig kudzu off	
[root@fc1-node1 root]# chkconfig netfs off	
[root@fc1-node1 root]# chkconfig nfs off	
[root@fc1-node1 root]# chkconfig nfslock off	
Iroot#ic1-node1 root]# chkconfig prmcia off	
Irootercl-nodel rootl# chkconfig portmap off	
Trooterci-hoader rootig cakconing ransa ori	
Front ff c1-model root 1# Chkconfig sastadtha off	
[root0fc1-mode1 root]# chkconfig smartd off	
[root@fc1-node1 root]# chkconfig yum off	
[root@fc1-node1 root]# reboot_	

To see the effect of disabling these services, the PC will need to be rebooted.

At the system prompt, enter the "reboot" command.

Action	At the system prompt, enter the "reboot" command, and press
Action	enter

This completes the customisation of the default Yarrow installation. The PC will now reboot, and you can move on to the openMosix installation.

4.7 Install openMosix

The following steps will convert your new Yarrow PC into an openMosix node.

Once again the PC will boot to the usual boot menu.



The default option is correct. You can either choose to let it time-out (after about 10 seconds) or you can press enter.

At the "Boot Menu" screen, press enter.

Ction At the Boot Menu screen, press enter

The PC will proceed to boot the Yarrow OS, where you can then login as root.

🔤 Command Prompt 📃	
<pre>>scp openmosix* root@192.168.100.11:/tmp/ The server's host key is not cached in the registry. You have no guarantee that the server is the computer you think it is. The server's rsa2 key fingerprint is: ssh-rsa 1024 c0:d7:75:62:ea:41:4d:80:9e:72:fc:81:fc:b5:ff:98 If you trust this host, enter "y" to add the key to PuTTY's cache and carry on connecting. If you want to carry on connecting. If you want to carry on connecting just once, without adding the key to the cache, enter "n". If you do not trust this host, press Return to abandon the connection. Store key in cache? (y/n) y root@192.168.100.11's password: openmosix-kernel-2.4.26-o 9269 kB 1544.8 kB/s ETA: 00:00:00 100% openmosix-tools-0.3.6-2.i 166 kB 166.3 kB/s ETA: 00:00:00 100% ></pre>	

Depending on how you've chosen to supply the two openMosix packages to your PC, this action may not apply.

For this example, the two openMosix packages have been downloaded from the Internet, onto a PC connected to the cluster LAN. Thus, the two openMosix packages are able to be "secure copied" to the new Yarrow PC.

At the system prompt of the Internet PC, enter "scp openmosix* root@192.168.100.11:/tmp/", accepting the new key and entering the new Yarrow system's root password.

Action	At the Internet PC's system prompt, enter the secure copy command "scp openmosix* root@192.168.100.11:/tmp/", and press enter; Accept the new SSH key, then enter the new Yarrow PC's
	root password "password", and press enter

The Internet PC will transfer the two openMosix packages to the new Yarrow PC's /tmp directory.



Its time to returning to the new Yarrow PC to install the openMosix packages.

Install the openMosix kernel by entering the command "rpm –ivh /tmp/openmosix-kernel-2.4.26-openmosix1.i386.rpm".

	At the Yarrow PC's system prompt, enter the openMosix kernel
Action	installation command "rpm -ivh /tmp/openmosix-kernel-2.4.26-
	openmosix1.i386.rpm", and press enter

Install the openMosix tools by entering the command "rpm –ivh /tmp/openmosix-tools-0.3.6-2.i386.rpm".

	Then, at the system prompt, enter the openMosix kernel
Action	installation command "rpm -ivh /tmp/openmosix-tools-0.3.6-
	2.i386.rpm", and press enter

To make the openMosix kernel the default boot kernel, you will need to edit the boot loader. Use your favourite unix text editor – this document refers to "vi".

Action	At the system prompt, enter the boot loader configuration
Action	editor command "vi /etc/grub.conf", and press enter

The editor will then open the /etc/grub.conf file for editing.

Unrestricted Distribution

👜 FC1 Node1 - VMware Workstation 📃 🗖 🔀
File Edit View VM Team Windows Help
grub.conf generated by anaconda
<pre># Note that you do not have to rerun grub after making changes to this file # NOTICE: You do not have a /boot partition. This means that # all kernel and initrd paths are relative to /, eg. # root (hd0,0) # kernel /boot/vmlinuz-version ro root=/dev/sda1 # initrd /boot/initrd-version.img</pre>
#boot=/dev/sda default=0 timeout=10
splashimage=(hd0,0)/boot/grub/splash.xpm.gz title Fedora Core (2.4.26-openmosix1) root (hd0,0) kernel /boot/vmlinuz-2.4.26-openmosix1 ro root=LABEL=/ hdc=ide-scsi
initrd /boot/initrd-2.4.26-openmosix1.img title Fedora Core (2.4.22-1.2115.nptl) root (hd0,0) kernel /boot/vmlinuz-2.4.22-1.2115.nptl ro root=LABEL=/ hdc=ide-scsi initrd /boot/initrd-2.4.22-1.2115.nptl.img

With the text editor open on the boot loader configuration file (/etc/grub.conf) you can change the default kernel image. To do this, change the line "default=1" to "default=0", and save the configuration file.

Action	Within the text editor "vi", use the "arrow" keys to move the cursor to the "1" in the "default=1" line, then enter "cl" (for "c"hange "l"etter), then enter the number "0". To exit the
	program, saving the changes, press the "ESC" key, then enter ":wq" and press enter

The boot loader (Grub) now has the correct configuration file, but the installed Grub boot loader needs to be updated with the changes.



Install the new configuration into the boot loader with the command "grub-install /dev/sda". Note that "/dev/sda" should be replaced with the value of the disk device as noted in the Boot Loader Configuration OS screen, for your installation.

Action	At the system prompt, enter the boot loader installation
ACIION	command "grub-install /dev/sda", then press enter

The boot loader (Grub) now has been installed with the correct configuration. The system is ready to be rebooted.

Action	At the system prompt, enter reboot command "reboot", then press
Action	enter

This new Yarrow system will now boot as a fully operational openMosix node.

4.8 Re-use these steps

These installation steps (all of section 4) will be repeated for each new PC that you would like to build as an openMosix node. All that is required is a new IP address and a new name to be selected, per PC/node.

|--|

You must successfully complete the installation of at least two nodes before continuing past this point.

Action	Do not	continue	past	this	point	until	you	have	two	nodes	

5 Building the cluster

5.1 Cluster construction notes

Please note that the following steps are not mandatory. They have been included to provide a means for you to validate the successful operation of your new cluster, and to show you how the cluster is formed, automatically, from a number of nodes on a single LAN segment (or two nodes on a cross-over cable).

This section does assume that you have built two (2) nodes, per the instructions in the previous section. The first node is fc1-node1 at 192.168.100.11, and the second is fc1-node2 at 192.168.100.55.

5.2 Build the cluster

Start with both nodes powered off.

Boot the first node, and wait until it displays the boot menu. If the node has been built correctly, the default boot option will be the openMosix kernel for your Yarrow OS.



The default option is correct. You can either choose to let it time-out (after about 10 seconds) or you can press enter. At the "Boot Menu" screen, press enter.

At the Boot Menu screen, press ent

The PC will proceed to boot the Yarrow OS, where you can then login as root.



The "openMosix map" is the record that details what nodes are included in the cluster, by IP address. The map itself is stored within the openMosix kernel. To see the openMosix map, at the system prompt, run the command "showmap".

Action	$\lambda + + h \circ$	avatom	prompt	ontor	+ho	aommand	"chouman"	prece	ontor
ACTION	AL LIIE	system	prompt,	enter	une	Command	snowillap,	press	enter

As only one node has been booted on this LAN, the map will show one IP address with a count of 1 node – this node.



Shutting down the first node, and repeating the boot, logon and showmap command sequence on the second node, you will see that there is only one node here, too; the local node.

Action	Shut-down the first node, from its system prompt, with the following command "shutdown $-g0 -y -i0"$, and press enter; boot
	the second node, login to it as root, then at its system prompt, enter the command "showmap", press enter

As only one node has been booted on this LAN, the map will show one IP address with a count of one node – this node.

FC1 Node1 - VMware Workstation					
File Edit View VM Team Windows Hel	p				
🚡 Home 🔒 FC1 Node1 📑 FC1 Node2	×				
Fedora Core release 1 (Yarrow) Kernel 2.4.26-openmosi×1 on an i686 fc1-node1 login: root Password: Last login: Mon Mar 27 23:26:14 on tty1 [root@fc1-node1 root]# showmap Mu Node-Id: 0x640b					
Base Node-Id Address	Count				
8×640b 192.168.100.11 8×6437 192.168.100.55 [root@fc1-node1 root]# _	1 1				

Leaving the second node alone, boot the first node. By the time you have logged in to the system as root, and executed "showmap", you should find that two nodes have been recorded in the node's cluster map.

Action	Boot the first node, logon, and then, from that node's system
	prompt, enter the following command "showmap", and press enter

As both nodes have been booted on this LAN, the map will show two IP addresses with a count of 1 node each – this node (the first node) and the other node (the second node).

FC1 Node2 - VMware Workstation File Edit View VM Team Windows Help 🔺 Home 🛛 🖶 FC1 Node1 🛛 🖶 FC1 Node2 Fedora Core release 1 (Yarrow) Kernel 2.4.26-openmosix1 on an i686 fc1-node2 login: root Password: Lass login: Mon Mar 27 23:39:59 on tty1 [root@fc1-node2 root]# showmap My Node-Id: 0x6437 Base Node-Id Address Count 192.168.100.55 1 0x6437 [root@fc1-node2 root]# openMosix configuration changed: This is openMosix #25655 (of 2 configured) openMosix #25655 is at IP address 192.168.100.55 openMosix #25611 is at IP address 192.168.100.11

Returning to the second node, an openMosix kernel message should have been output to the screen, beginning "openMosix configuration changed". This message should show the node numbers and their IP addresses as logged at the moment of discovery.

Note the two IP addresses, one for the local node (the second node) and one for the other node (the first node).

🗐 FC1 Node2 - VN	lware Workstation		- 0 🗙	
File Edit View V	/M Team Windows Help			
🔒 Home 📑 FC1 N	lode1 🔐 FC1 Node2		×	
Fedora Core r Kernel 2.4.26	elease 1 (Yarrow) -openmosix1 on ar) n 1686		
fc1-node2 log	in: root			
Password: Last login: M [root@fc1-nod My Node-Id: Ø	on Mar 27 23:39:5 e2 root]# showmar x6437	59 on tty1 p		
Base Node-Id	Address	Count		
0x6437 192.168.100.55 1 [rootOfc1-node2 root]# openMosix configuration changed: This is openMosix #25655 (of 2 configured) openMosix #25655 is at IP address 192.168.100.55 openMosix #25611 is at IP address 192.168.100.11				
[root@fc1-node2 root]# showmap My Node-Id: 0x6437				
Base Node-Id	Address	Count		
Øx6437 Øx640b [root@fc1-nod	192.168.100.55 192.168.100.11 e2 root]# _	1 1		

Staying with the second node, running "showmap" will show the kernel's openMosix map – confirming that there are now two nodes in the openMosix map on both nodes.

Action At the system prompt, enter the command "showmap", press enter

As both nodes have been booted on this LAN, the map will show two IP addresses with a count of 1 node each – this node (the second node) and the other node (the first node).

Both nodes must have the same cluster map. The example cluster has met that prerequisite. The next step is to test the cluster, and its process migration.
5.3 Test the cluster

Start with both nodes powered on. If you are testing your cluster from first principles then you should have successfully passed the "showmap" tests above.

For the purposes of this test, the selection of a node is arbitrary as either node will operate as a "home node". However, for ease of reference, return to the first node.



You are going to create a small perl script that will endlessly consume processor resources. To create this script, open a new text file in your unix text editor with the command "vi /tmp/omtest.sh".

Action	On the first node, at the system prompt, enter the editor
	command "vi /tmp/omtest.sh", press enter

This will cause the editor to open a new editor window for the file /tmp/omtest.sh.



With the text editor open on the new script file (/tmp/omtest.sh) you can insert the script commands. To do this, press "i", enter the script as shown, then save by pressing "ESC", ":wq".

```
Within the text editor "vi", enter "i" (for "i"nsert), then
type the following seven lines, pressing enter at the end of
each line;
#!/usr/bin/perl
$i=1;
while($i) {
    $i++;
    }
To exit the script, saving the changes, press the "ESC" key,
then enter ":wq" and press enter
```

The file /tmp/omtest.sh now contains a resource hungry perl script.



The new script is not executable, by default. This needs to be corrected; enter the following permission changing command "chmod 755 /tmp/omtest.sh".

Action	At the system prompt, enter the permission changing command
Action	"chmod 755 /tmp/omtest.sh", then press enter

The script is now ready to run. Running multiple instances of the script will help to overload the local node, forcing it to consider pushing one or more instances of the script to the "less busy" node.

Multiple instances can be run by using the shell "&" directive, to put the command into the background.

	At the system prompt, enter the command "/tmp/omtest.sh &", and
Action	press enter; repeat this sequence for a total of four script
	Taunches

There should now be four running instances of "omtest.sh". This program, being very processor hungry should have some instances pushed over to the second node.

FC1 Node1 - VMware Workstation	
File Edit View VM Team Windows	Help
🚡 Home 📑 FC1 Node1 📑 FC1 Node2	×
1.26 0.94	
L 0 0.63	
A D 0.31	
0 Node # 25611 25655	

To see the load of each node in the cluster, from any node in the cluster, run the command "mosmon" – try this now, staying on the first node. Shown in this screen shot, the first node believes that both nodes are evenly distributing the load – indicating that there are two "omtest.sh" script instances on each node.

Action At the system prompt (still on the first node), enter the command "mosmon", and press enter	
--	--

You are now able to clearly see the load of your cluster, in a single screen. This process should be repeatable on any node, so try now on the second node.

👰 F	C1 No	de 2 - V	/Mwai	e Wo	kstation	
File	Edit	View	VM	Team	Windows	Help
<u>п</u> н	lome	FC1	Node1		FC1 Node2	×
1	.26 .94					
L 0 0	.63					
A D Ø	.31					
Node	е#	256	511 2	25659	5	

Move to the second node. At the system prompt run the command "mosmon". You should see an identical load display to the first node.

Action	At the system prompt (on the second node), enter the command
	"mosmon", and press enter

You are now able to clearly see the load of your cluster, in a single screen; from either node.

Congratulations, you have just confirmed that your cluster is working completely.

6 Conclusion

This paper provides a basic, step-by-step process for installing a working openMosix cluster. It uses only an off-the-shelf Linux distribution and two openMosix RPMs, requiring no code modification or compiling whatsoever.

This process is repeatable. It requires no prior openMosix experience.

While this documentation is not intended to produce a production cluster, it is hoped that it will provide a solid point from which to help some users perform cluster configuration or cluster network debugging. It is hoped that this document will help most new openMosix users to understand the openMosix node and cluster configuration in a "clean" environment, allowing them to help themselves – to adapt a working model to their own environments.

If this paper saves one person the frustration of debugging a foreign operating environment in a foreign network environment, then it has been worth every page.

7 References

7.1 Distributions

7.1.1 Fedora Core 1 (AKA: Yarrow)

http://download.fedora.redhat.com/pub/fedora/linux/core/1/

7.2 Software

7.2.1 openMosix

http://www.openmosix.org/

8 Contact

8.1 Additions, Modifications and Deletions

For changes to this document, please refer to the author and revision history blocks in the control page. Please report errors or omissions to the author.

8.2 Consultation

If you would like to discuss openMosix installation or other concepts related to this white paper, then please contact the author;

Ian Latter Late night coder ... Midnight Code Email: Ian.Latter@midnightcode.org